

IceWarp Unified Communications

IceWarp Server Outlook Sync User Guide

Version 11.1

IceWarp[®]



Published on 1/6/2015

Contents

IceWarp Outlook Sync User Guide 4

Installation	5
Installation Pre-requisites	5
Installation Modes	5
Installation Step-by-Step	6
Activation.....	11
Installation Crossroads	12
Upgrade from Outlook Connector	13
Import of .pst Backup File	13
Folder Sharing – Folder Access Rights	14
Troubleshooting	17
IceWarp Outlook Sync versus AntiVirus	17
Missing Installation Prerequisite File(s)	17
Vista Installation Issue	17
IceWarp Options.....	18
Profile Manager	18
New Profile	18
GroupWare Only Profile	21
IceWarp License	22
Online Activation	23
Offline Activation	24
Synchronize.....	24
Folder Sync.....	25
Settings	26
Login Credentials	26
Advanced	28
Synchronization	30
Appearance.....	32
License and Updates.....	34
Logs.....	35
About	36
Rules	37
Responder.....	44
Bind Profile	45
Non POP3 Account Binding Scenario	46

Miscellaneous	48
Clean Ignore List.....	48
Show in Address Book.....	49
Access Control List – Inherit	49
Folder/Account Subscription	49
Uninstallation	51
Advanced IceWarp Outlook Sync Background.....	52
About	52
Mass Installations	52
Command Prompt Installations	52
Synchronization Progress Window	53

IceWarp Outlook Sync User Guide

Registered Trademarks

iPhone, iPad, Mac, OS X are trademarks of Apple Inc., registered in the U.S. and other countries. Microsoft, Windows, Outlook and Windows Phone are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. Android is a trademark of Google Inc. IceWarp is a registered trademark in the USA and other countries.

Installation

This chapter lists installation pre-requisites and details step-by-step installation procedure.

Installation Pre-requisites

- Microsoft Outlook must be installed on the machine where you want to install IceWarp Outlook Sync, but it must not be running. (In the case more users share one machine, all Outlook instances must be killed.)



NOTE: There are times when MS Outlook appears not to be running but it actually is. You can check it by looking for **OUTLOOK.EXE** in the Windows Task Manager. If it is listed, shut it down (**End Task**) before you start installation.

- You should be familiar with MS Outlook.
- If using Windows XP, you need to have Service Pack 3 installed.
- You should have your account name, password, and server name (hostname) at hand – you will need these to configure your account.
- You should have downloaded the latest version of the IceWarp Outlook Sync from the IceWarp web site or from your local provider of IceWarp Server (e.g. <http://mydomain.com/install/>) or from the WebClient interface in the **Tools – Licenses/Integration – IceWarp Outlook Sync** section.
- You need to have installed .NET Framework version 3.5.1.



Even if you have .NET Framework version 4 installed, you still need to install also version 3.5.1.



If you intend to use the **.msi** installation file format, you will just be asked whether you want to install it.

- You need **Activation Key** for its registration, e-mailed from your administrator or available from the WebClient interface in toolbar: **Tools – Licenses/Integration – IceWarp Outlook Sync** section. This is not necessary when you will use the **SmartDiscover** feature within the installation.
- You may be required to insert your original MS Outlook installation media. Make sure that you have your original MS Outlook installation media available before you intend to change your Outlook configuration.
- It is necessary to have administrative rights when installing IceWarp Outlook Sync on a whole (shared) machine. For installation to an individual user space, administrative rights are not required.
- Assure, you have sufficient disk space (depending on your email box size) – if you are not sure, ask your server administrator what is adequate.



For smooth IceWarp Outlook Sync function, it is necessary users to install every important MS Outlook update offered by Microsoft.

Installation Modes

For All Users

It works the same way as the old installer. It installs Outlook Sync to *Program Files* and uses a local machine registry. It still requires administrative rights. This mode also allows administrators to install prerequisites before the main installation commences.

Current User Only

Outlook Sync is installed to the *Application Data* folder and does not require administration privileges. This mode does not allow users to install prerequisites, because you still need administrative rights to install them.

Prerequisites

This mode offers missing prerequisites. Administrative rights are still required.



NOTE: There is no need to create a new profile if you want to switch from a local machine installation to the current user installation. Such a user just needs to uninstall Outlook Sync and then reinstall it.

Installation Step-by-Step

To install IceWarp Outlook Sync successfully, follow these steps:

1. Launch the latest IceWarp Outlook Sync installer. In the case you have any previous version installed, you will be offered to **Update/Uninstall** it. Perform upgrade (wizard will guide you).



NOTE: There are two types of installation files available. The **.msi** file and **.exe** one. Use the **.exe** file for usual client-based installations and **.msi** one for mass installations launched from a server.

2. On the **Welcome** page, select the installation and IceWarp Outlook Sync language and click the **Next** button.

Figure 1 – Welcome Page




3. On the **Application license** page, tick the **I accept the license agreement** box and click **Next**.
4. On the **Outlook Sync Advanced Setup** page, the installer detects the version of MS Outlook you use. (In the case you obtain any error message, contact your administrator. But, it is highly probable the detected version will be correct.)

From the **Installation type** list, select the appropriate option. For more information on installation types (modes), refer to the **Installation Pre-requisites – Installation Mode** section.

Click **Next**.


Figure 2 – Outlook Sync Advanced Setup Page



5. In the case the installer detects any required prerequisites missing, their list is shown on the **Prerequisites** page. Click the **Install** button. (Message is shown.)

These prerequisites are included in the installation package – you do not need to look for them anywhere.

Figure 3 – Prerequisites Page



NOTE: If you already have all items installed, this page is not shown.

6. On the **SmartDiscover** page, decide whether you want to use this feature.

Figure 4 – SmartDiscover Page

IceWarp® SmartDiscover ...

Email address:

Password:

Profile name:

Groupware only profile

Configure manually

Create profile

SmartDiscover – YES

- i. Fill in the **Email address**, **Password** and **Profile name** fields and click **Next**. The installer will obtain all information needed from the server.
- ii. In the next step, the **License activation** dialog is shown. If you have a license for IceWarp Outlook Sync on the server, click **Yes**. If not or if you want to use IceWarp Outlook Sync within the scope of 30 day trial period first, click **No**. You will proceed to the **Outlook Profile** page with its fields filled in. Also fields on the **Incoming Server** and **Outgoing Server** pages will be filled in. Just check that values are correct and click **Next**.

Figure 5 – License Activation Dialog

Setup will attempt to activate the product automatically. Skipping the activation will give you 30 days of free trial, but you will need to activate the license later. Do you wish to activate your license on this machine?

SmartDiscover – NO

- i. Tick the **Skip SmartDiscover and continue manually** box and click **Next**.
7. On the **Outlook Profile** page, fill in the **Profile name**, your **Email address** and **Display name** fields. Click **Next**.

Figure 6 – Outlook Profile Page

8. On the **Incoming server** page, enter your **Username**, **Password** and email server **Hostname** (or IP address).

By default, the **Port** number is 143.

Select what type of connection you want to use – either the **SSL (Secure Socket Layer)** (the **Port** number is 993) or **Start TLS (Transport Layer Security)** (the **Port** number is 143) options are recommended.

To test the entered values, you can click the **Test settings** button. The positive answer is desirable.

Click **Next**.

Figure 7 – Incoming Server Page

9. On the **Outgoing server** page, if the same server is used for outgoing emails, tick the **Use same as incoming** box. For **Port** numbers, see lower.

In the case of a different server, enter your **Username**, **Password** and email server **Hostname** (or IP address).


By default, the **Port** number is 25.

Select what type of connection you want to use – either the **SSL (Secure Socket Layer)** (the **Port** number is 465) or **Start TLS (Transport Layer Security)** (the **Port** number is 25) options are recommended.

To test the entered values, you can click the **Test settings** button. The positive answer is desirable.

Click **Next**.

Figure 8 – Outgoing Server Page



The screenshot shows the 'Outgoing SMTP server' configuration page in the IceWarp Outlook Sync interface. The page title is 'IceWarp® Outlook Sync login credentials ...'. The form contains the following fields and options:

- Username:** user
- Password:** masked with asterisks
- Hostname:** mail.icewarpdemo.com
- Port:** 25
- Start TLS (Transport Layer Sec):** Start TLS (Transport Layer Sec) (dropdown menu)
- Use same as incoming
- Test settings** button
- Cancel**, **<<< Back**, and **Next >>>** navigation buttons

10. On the **Select installation folder** page, the default installation folder is shown. If you want to change it, click the **Select** button and browse for the wished location. Click **Next**.
11. On the **Installation in progress** page, wait for the **Installation finished** message and click **Next**.
12. On the **Installation summary** page, click the **Finish** button to complete the installation.

Activation

After a successful installation, IceWarp Outlook Sync works in 30 day evaluation mode and will stop working if not activated before the evaluation period expires. To activate your license, have your activation key ready and proceed to the **IceWarp License** chapter for more information.

To check your license validity, select the **Add-Ins** tab – **Settings** button – **License** tab. See the **Settings** chapter – **License** section.

Installation Crossroads

This chapter describes possibilities how to "connect" IceWarp Outlook Sync with an email account and provides links to detailed procedures.

During IceWarp Outlook Sync Installation

This possibility allows you to connect IceWarp Outlook Sync with an existing account during IceWarp Outlook Sync installation. The whole procedure is described in the **Installation Step-by-Step** chapter.



NOTE: *This existing account has to be of the IMAP or POP3/IMAP type.*

After "No Profile" IceWarp Outlook Sync Installation

Mass or command line installations can be performed as "no profile" ones. It means that IceWarp Outlook Sync is installed but "Sync type" profile is not created. After this installation you can bind IceWarp Outlook Sync with an existing Outlook profile. Find detailed description in the **Bind this Profile with Server Account** chapter.

After Upgrade – Backup Data Import

This method is suitable either after upgrade from any previous "connector/sync" version or when you want to import a backup pst file. Procedures are described in the **Upgrade from Outlook Connector** chapter and **Import of .pst Backup File** one.

Upgrade from Outlook Connector

Actually, a "plain" upgrade is not available. The recommended way is to uninstall MS Outlook Connector, install IceWarp Outlook Sync, and activate the new license using the activation key. The activation key is the same as before, available from IceWarp WebClient or e-mailed from your administrator.



All user's data will be re-downloaded from the server to the new profile.

Follow these steps:

1. Uninstall Outlook Connector via **Control Panel – Programs and Features – Uninstall or change a program**, then install IceWarp Outlook Sync (see the **Installation Step-by-Step** (on page 6) chapter). This will create a new profile. All data then will be re-downloaded from the server to a new **pst** file.
2. To preserve an existing **pst** file, you need to back it up before un-installing (this is rather for someone who never used a Connector or stopped using it). Then run the IceWarp Outlook Sync installer – it will guide you to create a new Outlook profile.
3. If you wish to import data from your existing profile, mind not to name the new IceWarp Outlook Sync profile with the same name as the old one, as the old one would be deleted if names match.

Import of .pst Backup File

You may want to import data from the old MS Outlook profile to the new IceWarp Outlook Sync one using Outlook features for this (**File – Open – Import – Import from another program or file – Outlook Data File (pst)**). During this import, you can select folders that are to be imported – the old ones that do not exist on the server. In the case you will import the whole structure (including currently existing folders), folder items can be duplicated.




To avoid data duplication it is really easier to give up on importing and just uninstall, create a new profile and let it synchronize all data from the server. Outlook import feature can deal with import duplicities, but it is not sure, it will be 100% successful.

Folder Sharing – Folder Access Rights

You may want to share some of your IceWarp Outlook Sync folders to other users. To do it, follow these steps:

1. In the MS Outlook folder tree, select the folder you want to share, right-click it and select the **Folder Access Rights** item.

Figure 1 – Right-click Menu



The **Folder Access Rights** dialog opens.

Figure 2 – Folder Access Rights Dialog

- In the **Folder Access Rights** dialog, click the **Add** button. The **Select Users** dialog opens.

Figure 3 – Select Users Dialog

- In the **Select Users** dialog, highlight a user and click the **Select** button to place this user to the **Selected** field. Click **OK**.
- In the **Folder Access Rights** dialog, select access rights for individual users for both **Items** and **Folders**.
You can either select a combination from a list (**All, Full, Read, Write, None, Custom**) – in this case, these access rights apply for both **Items** and **Folders** – or tick the individual check boxes. Click **OK**.
- Repeat steps #3 and 4 for other wished users.



*NOTE: You may want to share whole your account. In this case, right-click the account name and select the **Account Access Rights** item. Continue with step #2.*

*NOTE: Do not set any rights for **Anyone** unless you want to grant access to all server users.*


*NOTE: To remove access rights, select a user in the **Folder Access Rights** dialog, click the **Remove** button and click **OK**.*

Access Right	Description (Item/Folder)
Administer	Full rights including the one to change permissions for this folder.
Read	Right to see items in the folder / folder itself respectively.
Write	Right to create/add new items into the folder / create new subfolders respectively.
Delete	Right to delete items included in the folder / delete subfolders respectively.
Modify	Right to modify items in the folder.

Troubleshooting

IceWarp Outlook Sync versus AntiVirus

In some cases, folder synchronization can last minutes. This is caused by an antivirus that checks incoming messages. During this time IceWarp Outlook Sync waits for an IMAP server response. If the situation occurs (it is not too often), you will see a message similar to this one:



Solution

To resolve this problem, disable email checking in your desktop antivirus program. As your IceWarp Server provides this service too, you need not to be afraid of doing this.

You may want to have your outgoing messages checked by your antivirus program because it attaches a short message to them to ensure recipients that messages are safe.

It is possible as outgoing messages check does not cause synchronization delays. You can disable only incoming messages check, provided that your antivirus program supports it.

Missing Installation Prerequisite File(s)

During an Outlook Sync launch, you may obtain an error message announcing that some file (library etc.) is missing. This situation can be caused by incomplete or corrupted update of your operating system (or e. g. Service Pack 3 in the case you are using Windows XP).

Solution

Download the appropriate file and place it to the correct directory. If the problem persists, contact your administrator.

Vista Installation Issue


You can obtain the ***Insufficient Rights*** error message when installing IceWarp Outlook Sync under Windows Vista.

Solution

It is necessary to run installation as ***Administrator*** or within an account with administrator permission.

IceWarp Options

After a successful installation, a new tab appears in the main menu of MS Outlook. Its name is **IceWarp Sync**. This is the place where to manage IceWarp Outlook Sync settings.



In the case IceWarp Outlook Sync is not bound with any existing profile, this tab is different:



NOTE: In the case you use MS Outlook 2007, find these options under the **Tools** main menu item.

Profile Manager


New Profile

Clicking the *New Profile* button allows you to create a new IceWarp Outlook Sync profile using a profile manager. This situation can apply in the case two or more users share one computer, one of them has installed IceWarp Outlook Sync and others have their accounts that have not been bound to any "Connector" or "Sync" type profile.

Follow these steps:

1. Click the button. The **Create new profile** dialog appears. Click the **Yes** button.

Figure 1 – Create New Profile Dialog



2. On the **Create new profile** page, click the **Next** button.
3. On the **SmartDiscover** page, decide whether you want to use the SmartDiscover feature.
 - In the case you want to use it, fill in the *Email address*, *Password* and *Profile name* fields and **DO NOT** tick the *Configure manually* box. Click *Next*.

Figure 2 – SmartDiscover Page

IceWarp® SmartDiscover ...

Email address: f.drake@icewarpdemo.cz

Password: *****

Profile name: f.drake@icewarpdemo.cz Outlook Sync

Groupware only profile

Configure manually

Cancel <<< Back Next >>>

In the next step, select whether you want to activate license or use a trial version up to 30 days. On the next page, click the *Finish* button.

- In the case you do not want to use SmartDiscover feature, tick the *Skip SmartDiscover and configure manually* box and click *Next*. You will proceed to the **Outlook Profile** page.
4. On the **Outlook Profile** page, fill in the **Profile name**, **Email address** and **Display name** fields. Click the **Next** button.

Figure 3 – Outlook Profile Page

IceWarp® Outlook Profile ...

Profile name: Francis Drake


Email address: f.drake@icewarpdemo.cz

Display name: Francis Drake

Cancel <<< Back Next >>>

5. On the **Outlook Sync login credentials – Incoming server** page, fill in your **Username**, **Password**, server **Hostname** and **Port**. For more information about server settings and the **Use SSL security** check box, refer to the [Installation Step-by-Step](#) chapter – step # 7. Click the **Next** button.

Figure 4 – Incoming Server Page




The screenshot shows the 'Incoming server' configuration page in the IceWarp Outlook Sync interface. The page title is 'IceWarp® Outlook Sync login credentials ...'. The form contains the following fields and controls:

- Username:** f.drake
- Password:** [Redacted]
- Hostname:** icewarpdemo.cz
- Port:** 143
- Start TLS (Transport Layer Sec):** [Dropdown menu]
- Buttons:** 'Test settings', 'Cancel', '<<< Back', and 'Next >>>'.

6. On the **Outlook Sync login credentials – Outgoing server** page, tick the **Use same as incoming** box (if the same server is used for outgoing emails) or fill in your **Username**, **Password**, server **Hostname** and **Port**. For more information about server settings and the **Use SSL security** check box, refer to the [Installation Step-by-Step](#) chapter – step # 8. Click the **Next** button.

Figure 5 – Outgoing Server Page




The screenshot shows the 'Outgoing SMTP server' configuration page in the IceWarp Outlook Sync interface. The page title is 'IceWarp® Outlook Sync login credentials ...'. The form contains the following fields and controls:

- Username:** f.drake
- Password:** [Redacted]
- Hostname:** icewarpdemo.cz
- Port:** 25
- Start TLS (Transport Layer Sec):** [Dropdown menu]
- Use same as incoming:**
- Buttons:** 'Test settings', 'Cancel', '<<< Back', and 'Next >>>'.

7. On the **New profile summary** page, click the **Finish** button.

Figure 6 – New Profile Summary Page



GroupWare Only Profile


Usually, the IceWarp Outlook Sync profile is created as the IMAP one. But, you may want to download your email messages to your computer (email client).

This feature – GroupWare only profile – allows you to create a POP3 profile combined with synchronization of your groupware items.

To create this profile combination, follow these steps:

1. Use the *Profile Manager GroupWare Only* link (**Windows 8 – Applications** screen).
2. Follow the steps # 2 to 6 of the previous procedure.
3. On the **Incoming POP3 server** page, review the shown information. (In the case your outgoing POP3 mail server differs from the incoming one, untick the *Use same as incoming* box. The **Outgoing POP3 server** page is shown – it is very similar to the page shown at the step # 6 of the previous procedure.)

BE AWARE: POP3 offers only plain (unsecured) or SSL access – apart from other services offering also STARTTLS. Please review POP3 line security settings before creating groupware only profile. In doubts, contact your administrator.



The screenshot shows the 'IceWarp Outlook Sync login credentials' configuration window. The window has a title bar with the IceWarp logo and the text 'Outlook Sync login credentials ...'. Below the title bar, there is a section titled 'Incoming POP3 server' with the following fields and options:

- Username:** A text input field containing 'f.drake'.
- Hostname:** A text input field containing 'icewarpdemo.cz'.
- Port:** A spin box containing '995'.
- SSL (Secure Socket Layer):** A dropdown menu currently set to 'SSL (Secure Socket Layer)'.
- Use same as incoming**

At the bottom right of the configuration area is a 'Test settings' button. At the bottom of the window are three navigation buttons: 'Cancel', '<<< Back', and 'Next >>>'. The 'Next >>>' button is highlighted with a blue border.

Click *Next*.

4. On the **New profile summary** page, click the *Finish* button.

IceWarp License

Clicking this button reveals the **License** dialog. On the **License** tab (see the **Activation** chapter), you can check your license validity. If it reads **License subscription expires on ...** with some date in near future, you need to activate your license.

Two other tabs let you activate your license either online or offline.


Online Activation

To activate your license online, follow these steps:

1. Obtain your activation key from your administrator.

Another way is to get it via IceWarp WebClient: Within the **Communication Bar – Options** dialog, select the **Licenses** tab – *Outlook Sync* item. From the *Product Activation Key* field, copy your activation key.

Figure 1 – IceWarp WebClient – Options – Licenses




2. Within the **MS Outlook – IceWarp Sync** tab – **License** dialog, select the **Online Activation** tab.

Paste your activation key into the *Activation Key* field.

Click the **Activate License** button. The button will only be active if you enter a correctly formatted activation key.

Figure 2 – License Dialog – Online Activation Tab



Click **OK** to finish activation.

3. An error message is shown in the case the activation failed.

License registration may fail for the following reasons:

- The activation key is expired – obtain a new one and repeat the registration.
- The computer is blocked from accessing the Internet or access to the licensing server is temporarily unavailable.
- The number of client licenses has been exceeded for your organization. IceWarp licensing servers track how many systems have been activated using a given license. If the number of activated clients exceeds the total for the license, IceWarp Outlook Sync will inform you that additional licenses need to be purchased.

- If you need to re-install IceWarp Outlook Sync software on a new system due to either hardware failure or system upgrade, contact your support staff to assist you with removing the existing IceWarp Outlook Sync registration, or request a new activation key.

Offline Activation

To activate your license offline, follow these steps:

1. To register IceWarp Outlook Sync off-line (because your computer cannot access the license server), you need to obtain the **license.xml** file from IceWarp website.

Go to <http://www.icewarp.com/purchase/>, click the **Lic. Maintenance** button and in the **Client License Activation** section, click the **Activate License** button.

2. Copy the content of the **Identification Key** field (**License dialog – Online Activation tab** (see the above figure)) and paste it into the web page field of the same name.

Copy your activation key and paste it into the **Activation Key** web page field.


Click the **Next** button.

3. On the next page, click the link to download your **license.xml** file and save it into the wished directory.

4. In the IceWarp Outlook Sync **License dialog – Enter License Offline** tab, click the **Enter License File** button.

Browse for the **license.xml** file and click **Open**.

Figure 3 – Entering license.xml File



Click **OK** to finish activation.

If you are unable to register the IceWarp Outlook Sync, contact your support helpdesk or IT administrator, please.

Synchronize



Synchronize

Within the **Home** tab, click this button to synchronize items in the selected folder immediately.

Folder Sync



Folder
Sync

Within the **Home** tab, click the button to synchronize whole folder structure (added or deleted folders) immediately.


Settings

Login Credentials

This tab allows you to manage your login to a server and connection with it.

Field	Description
Username	Enter your username for your mail server. It is filled in during installation.
Password	Enter your password for your mail server. It is filled in during installation. If changed after installation, change it also here.
Email address	Enter your email address. It is filled in during installation.
Remember password	Tick the box if you do not want to be asked for your password always when you launch IceWarp Outlook Sync.
Do not show login errors	Tick the box if you do not want to have shown messages in the case, IceWarp Outlook Sync cannot login to the server.
Change password	Click the button to open a usual dialog for a password change.
Hostname	Enter the hostname of your mail server.
Port	The default port number for IMAP service is 143.

<p><i>Connection type selection</i></p>	<p>Select the appropriate connection type:</p> <ul style="list-style-type: none"> • <i>Unsecured line (not recommended)</i> – the connection is not encrypted at all. • <i>Start TLS (Transport Layer Security)</i> – first attempt to establish connection is done by usual (non-encrypted) communication. After connection establishing, encrypted communication is used. • <i>SSL (Secure Socket Layer)</i> – the connection is fully encrypted. By default, the SSL port of 993 is used.
<p>Manage certificates</p>	<p>Click the button to open the Manage certificates dialog – see lower. Select an unwished (approved) certificate and click the <i>Remove</i> button to delete this certificate.</p>
<p>Do not show connection errors</p>	<p>Tick the box if you do not want to have shown messages in the case, IceWarp Outlook Sync cannot connect the server.</p>



Advanced

This tab allows you to manage advanced settings. Usually it is not necessary to change default values. If in doubt, consult with your administrator.

Field	Description
Authentication type	<p>Select authentication type you want to use:</p> <ul style="list-style-type: none"> ▪ Cram MD5 – server sends a string, credentials to be encrypted with by a client. Encrypted credentials are sent to the server. It encrypts saved credentials with the same string and compares results. ▪ Plain – no encryption (or base64) is used.
Conflict resolution	<p>It is possible to access a server using two (or even more) clients in the same time. When some item (contact, event, etc.) is changed from one client, and changed to a different value from the other one, the solution can be:</p> <ul style="list-style-type: none"> ▪ Server wins – the data on the server are used in the case of conflict. ▪ Client wins – the last data change wins in the case of conflict.
Full synchronization threshold	<p>Up to this number of emails, these items are parsed and synchronized. When number of emails exceeds this number, synchronization is based on Outlook information about items that need to be synchronized (i. e. have been changed). If there are many messages, Outlook Sync does not loop over all messages but deals with a change report provided by Outlook. Because Outlook sometimes does not inform about the changes, 100% functionality is guaranteed only if we loop over all emails.</p> <p>It is not recommended to set this value to much higher than 1024 because the processing is then very CPU consuming.</p>

Threshold for full download (MB)	Up to this email size (in megabytes), whole emails are downloaded. When email size exceeds this number, only email headers are downloaded. Whole emails are downloaded in the moment they are clicked (to open them). This field is enabled only when the Custom option (see lower) is selected.
Custom	Select one of the following: <ul style="list-style-type: none"> ▪ Custom – this option lets you to specify the Threshold for full download feature. ▪ Headers – only email headers will be fully downloaded. ▪ Full – all emails will be fully downloaded.
Download files fully	This feature is related to file type folders only. If the box is ticked, files are downloaded fully regardless of the download threshold set above.
Pause between processing (ms)	Specify a pause between processing of single items. Very advanced feature – do not set to 0 (zero).
Server port	Specify the port POP3 server to listen on. For more information about POP3 server, refer to the Advanced IceWarp Outlook Sync Background chapter.
Start/Stop	Click the buttons to start/stop this POP3 server. Do not do stop the server unless you exactly know what you want to do. For more information about POP3 server, refer to the Advanced IceWarp Outlook Sync Background chapter.
Disable TNEF (requires Outlook restart)	In the case you forward emails with HTML formatting and recipients complain they receive the winmail.dat file (it includes HTML formatting) or weirdly looking messages, tick this box to disable creating of this file – this solves the problem. <i>NOTE: It is necessary to restart Outlook to apply.</i>

Synchronization

This tab allows you to manage folder synchronization.

The screenshot shows the 'Synchronization' tab in the Outlook Sync settings window. The window has several tabs: 'Login credentials', 'Advanced', 'Synchronization', 'Appearance', 'License and updates', 'Logs', and 'About'. The 'Synchronization' tab is active.

Folders for automatic synchronization

- Calendar
- Contacts
- Documents
- Drafts [Not synchronized]
- INBOX [Always priority]
- Journal
- Notes
- Outbox [Controlled by Outlook]
- RSS Feeds

Synchronization frequency

Synchronize folder structure after N minutes: 60

Use Outlook Settings

Synchronize selected priority folders (red) after N minutes: 1

Synchronize selected standard folders after N minutes: 60

Synchronization exceptions

- Synchronize content of the selected folders immediately after local change is detected
- Synchronize Global Address Books automatically
- Do not show progress
- Automatically revert changes in read only folders

Buttons: Cancel, Ok

Field	Description
Folders for automatic synchronization	Tick folders that you want to have synchronized automatically. Other folders are synchronized when entered or when you select a manual synchronization (the Synchronize button).
Synchronize folder structure after N minutes	Select time in minutes. Folder structure (added or deleted folders) will be synchronized in this interval.
Use Outlook Settings	Tick this box if you want to use synchronization settings as set for the original Outlook POP3 account.
Synchronize selected priority folders after N minutes	Select time in minutes. Priority folders will be synchronized in this interval. By default, it is one minute. NOTE: To set a folder as a priority one, right-click it in the <i>Folders for automatic synchronization</i> list and select the <i>Priority sync</i> item. Priority folders are marked red.
Synchronize selected standard folders	Select time in minutes. Standard folders will be synchronized in this interval. By

after N minutes	default, it is 30 minutes.
Synchronize content of the selected folders immediately after local change is detected	Tick the box if you want to have selected folders synchronized immediately after performing (and saving) any change – e. g. after creating a new contact, event, etc.
Synchronize Global Address Books automatically	Tick the box if you want to have synchronized Global Address Books within standard folders interval. (Minimal interval is 60 minutes.)
Do not show progress	Tick the box if you do not want to have synchronization progress displayed.
Automatically revert changes in read only folders	Tick the box if you do not want to have maintained content of your read-only folders at the state as they exist on the server without having to deal with Outlook alerts.




NOTE: The **Drafts** folder cannot be synchronized.

Appearance

This tab allows you to select the IceWarp Outlook Sync language, as well as set new emails notifications.

Field	Description
Language	Select a wished language from the list.
Show desktop notification	Tick the box if you want to have shown notifications of incoming messages.
Delay before close (seconds)	Set how long time is this notification to be shown.
Play sound when new message arrives	Tick the box if you want to be notified by playing sound.
Select sound file	You may want to have another sound played. Use the "..." button to browse for the appropriate file. It should be of the .wav format. The adequate sound length is 1 – 1.5 second.
Default sound	Tick the box in the case you want to have the default sound played.

Test sound	Click the button if you want to test the sound you have selected.
Read receipts	Tick the box if you want to have handling of the read receipts active.
Handle read receipts	<p>Select a mode from the list:</p> <ul style="list-style-type: none"> ▪ <i>Ask me before sending a response</i> – after reading an email message, you will be asked whether a read confirmation should be sent (in the case a message sender has requested it). ▪ <i>Always send a response</i> – a read confirmation will be sent automatically (in the case a message sender has requested it). ▪ <i>Never send a response</i> – a read confirmation will not be sent at all.
Content of the read receipt	<p>Click the Edit button to change read receipt text. Simple editor opens.</p>  <p>You can use variables here, click the appropriate button(s) to enter them into the text.</p> <ul style="list-style-type: none"> ▪ <i>%TO%</i> – extracts a recipient from the original message (your name or email address in this case) and uses it on the appropriate place. ▪ <i>%SUBJECT%</i> – extracts a subject from the original message and uses it on the appropriate place. ▪ <i>%SENT%</i> – shows the time (date) when the original message was sent. ▪ <i>%READ%</i> – shows the time (date) when the original message was read. <p>Click the <i>Default</i> button for return to the original (default) text.</p>
Display Address Book names as	<p>Select from the list how you want to have Address Book names shown:</p> <ul style="list-style-type: none"> ▪ <i>Numbered structure</i> – reflect server folder structure ▪ <i>Folder name only</i> – contact folders are shown in alphabetical order ▪ <i>Full folder path</i> – folder names include parent folder (s) names (if applicable) ▪ <i>Outlook native</i> – Address Book names structure is fully controlled by Outlook

License and Updates

This is an alternative way how to manage your license. Clicking the **Open license dialog** button reveals this dialog. For details about it, refer to the **Activation** and **IceWarp License** chapters.

The **Updates** section is visible only if the logged user is able to install updates on that machine (i.e. he/she is either an administrator or the plugin is installed for a current user).

Tick the *Check for updates* box if you want to use **Automatic Updates**.

Outlook Sync license expiration date is also shown.

The screenshot shows a dialog box with several tabs: Login credentials, Advanced, Synchronization, Appearance, License and updates (selected), Logs, and About. The dialog is divided into three main sections:

- License information:** Shows "Expires on:" with the text "Never expires. You can get free upgrades till Monday, October 21, 2019."
- License dialog:** Contains a button labeled "Open license dialog".
- Updates:** Contains a checked checkbox for "Check for updates" and "Current version:" with the text "11.1.0.19014 (2014-10-27)". Below this is a button labeled "Check for updates".

At the bottom of the dialog are "Cancel" and "Ok" buttons.


Logs

This tab allows you to manage logging.

Field	Description
Logging level	Select level of logging: <ul style="list-style-type: none"> ▪ <i>Startup and errors only</i> – records only minimal amount of logs for basic troubleshooting ▪ <i>Debug</i> – provides detailed information about application behaviour
Show log directory	Click the button to open a directory with log files. Here you can find daily files with traffic logs. E. g. 07-24-2014.txt
Prepare logs from last two days	Clicking this button allows you to generate and save IceWarp Outlook Sync logs from last two days. In the case of problems, these logs are to be sent to IceWarp Technology (via your administrator).
Clear logs	Click the button to delete content of the current day log file.
Delete logs	Tick the box to enable automatic logs deletion.
Delete after specified days	Enter time period (in days) after what automatically generated logs will be deleted. This does not apply for logs generated by clicking the Prepare ... button.

About


This tab informs you about IceWarp Outlook Sync itself and its version.



Rules

Click the button to open the **IceWarp Options** dialog – **Rules** tab. Here you can create and edit rules that can help you to catch spam and viruses as well as to sort messages and direct them to wished folders.

Figure 1 – IceWarp Options Dialog – Rules



Field	Description
Check boxes	Tick the box(es) next to the rule(s) that you want to have active.
Add	Click the button to add a new rule. The Rule dialog opens.
Edit	Click the button to modify an existing rule. The Rule dialog opens.
Copy	Select a rule and click this button to copy the rule. This is handy when you want to create a similar rule.
Delete	Click the button to delete the selected rule. Multiple rules can be selected for deletion by holding the Ctrl key and clicking multiple rules. A range of rules can be selected by clicking the first rule of the range and then clicking the last one while holding down the Shift key.
Up/down arrows	Click the appropriate arrow to move the selected rule up or down. Order of rules in the list affects the order how they are performed.

Figure 2 – Rule Dialog

The screenshot shows the 'Rule Dialog' window with the following settings:

- Conditions:**
 - Where From: message header matches some words
 - Where To: message header matches some words
 - Where Subject: message header matches some words
 - Where Cc: message header matches some words
 - Where Reply-To: message header matches some words
 - Where Date: message header matches some words
 - Where Message priority is value
- Actions:**
 - Accept / Reject / Delete / Spam / Quarantine
 - Stop processing more rules
 - Forward to email address
 - Move to folder
 - Copy to folder
 - Encrypt message
 - Send message
- Description:**

Where From: message header matches navy
Move to Navy Project
- Title:**


navy project

Buttons:


Field	Description
Conditions	<p>In this area, you can select the properties of the message that you wish to perform some test on.</p> <ul style="list-style-type: none"> Multiple conditions can be tested by ticking multiple boxes. The same condition can be added multiple times by double clicking the condition when it is checked.
Actions	<p>In this area, you select the action(s) that you want to perform on the message if the rule evaluates as true.</p> <ul style="list-style-type: none"> Multiple actions can be selected by ticking multiple boxes.
Logic buttons	<p>The buttons below the Actions block are used to add logic to the rule</p> <ul style="list-style-type: none"> The exclamation mark will negate (NOT) the condition you are currently modifying. The up and down arrows will move the conditions up and down within the rule. The X button will delete the current condition. <p>We recommend experimentation with these buttons to familiarize yourself with their function.</p>
Description	<p>This will show the rule you are building or modifying and will change dynamically as you select or de-select conditions and actions.</p> <p><i>NOTE: Areas of the rules that can be modified are highlighted in this block and clicking them opens a further dialog box to allow you to define your test.</i></p>
Title	<p>The name of the rule – for identification purposes.</p>

The following table details individual conditions and actions.

Condition	Description
Where From: message header matches some words	Checks the From: header for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where To: message header matches some words	Checks the To: header for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where Subject: message header matches some words	Checks the Subject: header for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where Cc: message header matches some words	Checks the Cc: header for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where Reply-To: message header matches some words	Checks the Reply-To: header for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where Date: message header matches some words	Checks the Date: header for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where Message priority is value	Checks the priority of a message. In the rule description, click the Normal link to select a priority.
Where Message is spam	Checks if the message has been marked as spam.
Where Message is size	Checks the message size. Click the 0 kB link to select the message size criteria. Select Greater or Lower and specify its size (in kB).
Where Message body matches some words	Checks the message body for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where Custom message header matches some words	<p>Checks the Custom message header for a string condition.</p> <p>In the rule description, click the some words link to create the string condition (explained below).</p> <p>NOTE: This rule has an unusual format for the string condition!</p> <p>Format: <header>:<string condition></p> <p>where</p> <p><header> is the name of your custom header</p> <p><string condition> is the string condition to test for.</p> <p>Example: MyHeader:jim;bob;john</p> <p>Would check the "MyHeader" header for any of the strings "jim", "bob" or "john".</p>
Where Any message header matches some words	Checks all headers for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where Attachment name matches some words	Checks the attachment name for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where message contains attachment	Checks whether the message has an attachment.
Where Sender matches some words	Checks the sender for a string condition. In the rule description, click the some words link to create the string condition (explained below).

Where Recipient matches some words	Checks the recipient for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where sender/recipient is local/remote	<p>Checks the location of the sender or recipient. In the rule description click on local/remote to open the following dialog:</p> <p>Figure 3 – Sender/Recipient Dialog</p>  <p>Sender/Recipient</p> <p>Select whether you want to check the the sender or recipient address.</p> <p>Local / Remote</p> <p>Select whether you want whether the chosen address is a local account or a remote one.</p> <p>Ignore / Account exists / Account does not exist</p> <p>Select whether you want to check whether the account exists, does not exist, or ignore this check.</p> <p><i>Only available for local accounts.</i></p> <p>Member of:</p> <p>Checks whether the account belongs to a particular domain, group, mailing list, etc. Press the '...' button to open the Select Item dialog.</p> <p><i>Only available for local accounts that you check the existence or non-existence of.</i></p>
Where Sender's IP address matches some words	Checks the remote IP address for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where rDNS (PTR) matches some words	Checks the rDNS (PTR) record for a string condition. In the rule description, click the some words link to create the string condition (explained below).
Where Sender's IP address is trusted	Checks whether the Senders IP address is in the trusted list.
Where Spam score is value	In the rule description, click the 0.0 link to define a greater than or less than value to check the spam score against.
Where SMTP AUTH	Checks whether this message was delivered using an SMTP authorized connection.
Where Local time meets criteria	Checks whether a message meets time criteria defined in the Time Criteria dialog.
All messages	A special condition that evaluates TRUE for all messages – use with care!

String Testing	Description
	<p>Clicking the some words link (in a new condition) or the string itself (in a condition already defined) will open the String Condition dialog box.</p> <p>There are four options available in the dialog:</p> <p>The Function drop-down box offers six options for the string test, the option chosen effects the content required in the String text-box</p>
Contains list of strings (semi-colon separated)	Populate the String box with a list of strings to test for. Separate items using semicolons.
Matches (RegEx)	Populate the String box with a regular expression.
Starts with	Looks for the string specified in the String box at the start of the tested condition.
Ends with	Looks for the string specified in the String box at the end of the tested condition.
Equals	Tests whether the tested condition is exactly equal to the string specified in the String box.
Contains a value from a file or pattern	The String box should contain the path to a text file containing a list of strings you wish to test for. Press the "..." button to open a file dialog to navigate to a file where you can specify strings, one per line.
Match case	Check this box to take string case into account.
Match whole word only	Check this box to perform a standard "whole word" check against the string.
Actions	Description
	<p>The following actions are available when a condition is evaluated TRUE.</p> <p>Multiple actions can be selected by checking multiple boxes.</p> <p>Selecting an action will add the action to the Description area. For some actions you can click the text in the description to define the action further. Details follow:</p>
Reject/Accept/Delete/Spam/Quarantine	<p>Adds an action to reject (default) the message.</p> <p>Click the Reject link in the Description area to select Reject, Accept, Delete or mark the message as Spam.</p>
Stop processing more rules	Stops any further rules from being processed, if the rule connected with this action is evaluated as TRUE.
Forward to email address	<p>Forwards the message to an email address.</p> <p>Click the email address link in the Description area to specify the email address.</p> <p><i>You can also send an instant message or an sms using this option:</i></p> <p><i>sms – use sms:<number> e.g. sms:0123456789</i></p> <p><i>IM – use xmpp:<jabberid> e.g. bruce@icewarpdemo.com</i></p>
Move to folder	<p>Moves the message to a folder.</p> <p>Click the folder link in the Description area to select the folder to move to.</p> <p><i>Although the INBOX folder may be shown in the folder tree, there is little point selecting this folder as this is the default folder that messages will come in to.</i></p> <p><i>You can have email delivered to a specific mailbox folder by specifying</i></p>

	<p>%%Extension%% as the folder name. When this is specified IceWarp Server will look for a folder name within the email address and store the message to that folder if it exists.</p> <p>Example:</p> <p>A message sent to john:%%Important%%@icewarpdemo.com will be stored in the Important folder.</p> <p><i>Note the colon used to separate the user's alias from the folder name.</i></p>
<p>Copy to folder</p>	<p>Copy the message to a folder.</p> <p>Click the folder link in the Description area to select the folder to copy to.</p> <p><i>NOTE: Although the INBOX folder may be shown in the folder tree, there is little point selecting this folder as this is the default folder that messages will come in to.</i></p>
<p>Encrypt message</p>	<p>Check this option to have the message encrypted.</p> <p><i>NOTE: For this option to work there must be a copy of the user's public certificate located in a file called cert.pem in the user's mailbox folder. The message will be encrypted using this certificate and then can only be decrypted by the user using his private key in his email client.</i></p>
<p>Send message</p>	<p>Sends a message.</p> <p>Click the message link in the Description area to open a dialog to define the message.</p> <p>You can define To, From and Subject fields, the message text (or a file to retrieve the text from), the type of message (text, HTML, or message with an attachment) and whether the message is email, an instant message, or both.</p>
<p>Edit message header</p>	<p>Select this option to add, edit or delete a message header. Click the header link to open the Edit Message Headers dialog.</p> <p>Figure 4 – Edit Message Header Dialog</p>  <p>Click Add to add a new rule.</p> <p>Select an already defined rule and click Edit or Delete to modify or remove a rule.</p> <p>In the Action drop-down you should select whether this rule will add/edit a header or delete it.</p> <p>In the Header field you should specify the header you want to change/add – remember that the last header name character have to be a colon.</p>

	<p>You can also add your own named headers e.g. MyHeader:</p> <p>The first rule shown in the screenshot above modifies the From header - it adds the string "[URGENT]" to the beginning of the header. Note the use of the IceWarp Server system variable %%from%% here, which is the value of the original From header. Any system variable can be used.</p> <p>The second rule simply deletes the From header.</p>
Set message priority to value	Select this option to have the priority of the message changed. Click the Normal link to select the priority to be assigned.
Set message flags	Select this option to set a message flag. Click the flags to set the flag(s) you wish.

Responder

Click this button to open the **IceWarp Options** dialog – **Responder** tab. Here you can set how email messages will be replied during your absence.

Figure 1 – IceWarp Options Dialog – Responder

The screenshot shows the 'Responder' tab of the 'IceWarp Options' dialog. It features several configuration sections:

- Responder Mode:** A dropdown menu set to 'Respond once'.
- Respond again after (Days):** A text input field containing '0'.
- Respond only if between:** Two date pickers showing '2013/10/25' and '2013/12/05', each with a '...' button for selection.
- No Responder For:** A list box containing the email address 'alison@icewarpdemo.cz'.
- Responder Message:**
 - From:** dias@icewarp.com
 - Subject:** Re: %%Subject%%
 - Message text:** A text area containing:


```
Dear %%From_Name%%,
I cannot respond your email message because of my well-earned vacation.
I'll be back at my desk from November 6th. I'll be glad to help you.

Best regards,
Francis
```

At the bottom right, there are 'OK' and 'Cancel' buttons.

Field	Description
Mode	Select one of modes: <ul style="list-style-type: none"> ▪ Disabled – use this mode when you are at your desk – hard-working – or you do not want emails to be responded. ▪ Respond always – select this mode if you want every email message to be responded. ▪ Respond once – select this mode if you want every sender (email address) to be responded only once. ▪ Respond again after a period – select this mode if you want a response to the same sender to be sent after a period specified in the Respond again after (Days) field.
Respond again after (Days)	Select the Respond again after a period mode and fill in the appropriate period to this field. The message defined here will be sent to the same sender after this period. (Provided that this sender will send a new email.)
Respond only if between	Use the "..." buttons to specify a period when the message will be sent.
No Responder For	Enter email addresses of users that are to be excluded from these responses.

From	Fill in your email address.
Subject	Specify a response subject. It is possible to use the %%Subject%% variable. This will copy the original subject. See the figure above.
Message text	Word your response here. It is possible to use server variables within the message text. E. g. the %%From_Name%% one will copy the sender's name (see the figure above).

Bind Profile

This option is only accessible when IceWarp Outlook Sync is installed and the profile currently selected in MS Outlook is not bound to it.


This situation can also occur when you delete the account that was originally connected with IceWarp Outlook Sync during its installation. Another possibility is that you have installed IceWarp Outlook Sync using the command line with the **--noprofile** parameter. (For more information on this installation type, refer to the **Advanced IceWarp Outlook Sync Background** chapter.)



BE AWARE: Only accounts that use the POP3 protocol as the default one can be bound with IceWarp Outlook Sync profile.


How to Use

1. Launch MS Outlook. In the **Choose Profile** dialog, select the appropriate profile that you want to bind with IceWarp Outlook Sync.



Click the **OK** button.

2. On the Add-Ins tab, click the **Bind this profile with server account** button. The **Settings** dialog opens. Fill in all needed fields – see the **Settings** chapter.
3. During the first MS Outlook launch after IceWarp Outlook Sync installation, you may be presented with the **Initial Synchronization** dialog.



If your local Outlook **.pst** file includes any data (emails, contacts, etc.) – it probably does – and you want to keep them, click **No**.



This can cause duplication of some items (not necessarily).


If you want to delete all previous data, click **Yes**.

Non POP3 Account Binding Scenario

You may face the situation when you are using a non-POP3 account and you want to bind it with IceWarp Outlook Sync profile without a groupware data loss. This is also possible:

1. Within the existing profile (that includes your non-POP3 account), create a new "dummy" POP3 account and set it as a default one for this profile – select this account and click the **Set as Default** button.

Figure 1 – Account Settings Dialog – Set as Default



In MS Outlook 2007


IMAP account emails are stored on your server – no need to synchronize them. For groupware items (Contacts, Events, etc.), both accounts will use the same local Personal Folders. Later binding will synchronize them all to the server. Just click **No** when the **Initial Synchronization** dialog is shown (see step 3 of the **Bind Profile** chapter).

In MS Outlook 2010

When creating this dummy POP3 account, select the **Existing Outlook Data File** option, click the **Browse** button and select the appropriate **pst** file (**[profile_name].pst**). Groupware items (Contacts, Events, etc.) of both accounts are in this file and will be synchronized to the server. Just click **No** when the **Initial Synchronization** dialog is shown (see step 3 of the **Bind Profile** chapter).

Figure 2 – Add New Account – Existing Outlook Data File

POP and IMAP Account Settings
Enter the mail server settings for your account.



User Information	Test Account Settings
Your Name: <input type="text" value="BD"/>	We recommend that you test your account to ensure that the entries are correct.
Email Address: <input type="text" value="bd@icewarpdemo.cz"/>	<input type="button" value="Test Account Settings ..."/>
Server Information	<input checked="" type="checkbox"/> Automatically test account settings when Next is clicked
Account Type: <input type="text" value="POP3"/>	Deliver new messages to:
Incoming mail server: <input type="text" value="mail.icewarpdemo.cz"/>	<input type="radio"/> New Outlook Data File
Outgoing mail server (SMTP): <input type="text" value="mail.icewarpdemo.cz"/>	<input checked="" type="radio"/> Existing Outlook Data File
Logon Information	<input type="text" value="zuments\Outlook Files\Outlook3.pst"/> <input type="button" value="Browse"/>
User Name: <input type="text" value="bd"/>	<input type="button" value="More Settings ..."/>
Password: <input type="password" value="****"/>	
<input checked="" type="checkbox"/> Remember password	
<input type="checkbox"/> Require logon using Secure Password Authentication (SPA)	

< Back Next > Cancel


In MS Outlook 2013

Workflow is similar to the one described in the previous paragraph. When creating this dummy POP3 account, select the *Manual setup or additional server types* option and click *Next*, select *POP or IMAP* and click *Next*, and continue with selecting the *Existing Outlook Data File* option as described in the previous paragraph.

2. Install IceWarp Outlook Sync without creating a profile. This is possible using command line installation with the -- **noprofile** parameter – see the **Advanced IceWarp Outlook Sync Background chapter – Command Prompt Installations** section.
3. Perform binding of this POP3 account as described in the **Bind Profile** chapter.

Miscellaneous


Clean Ignore List



Sometimes, item download from a server to your email client can fail. When download fails three times, this item is included into an ignore list. Your email client does not attempt to download these items (emails, invitations, etc.).

After some time, the problem with this item(s) can be solved. In this case, you may want to download missing items. Select the appropriate folder, right-click its name and select **Clear Ignore List**. Missing items are downloaded.

Show in Address Book



You may want to add all contact from one folder to a common address book. Just right-click this contact folder and select the *Show in Address Book* item.


Access Control List – Inherit

When granting someone access to your folder you may want to use the *Inherit* button. This applies in the case the folder you want to share is a child folder of another folder already shared.

It is not necessary to choose the same access permissions for this folder. Just click this button. The ACL dialog gets grayed and the *Cancel Inheritance* button appears. (Use it to change access permissions.)

Folder/Account Subscription

In the case someone grants access either to a folder or account to you, you obtain an information e-mail. Clicking this message opens the **Access notification ...** dialog:




Field	Description
Decline	<p>Click the button to decline subscription. The information e-mail is deleted.</p> <p><i>NOTE: If you want to decline subscription but keep the information email, click the closing cross in the right-hand upper corner.</i></p>
Subscribe folder	<p>Click the button to subscribe the folder you have been granted access to. Your permissions are shown in the text field.</p> <p><i>NOTE: In the case you have been granted access to a whole account, this button is grayed.</i></p>
Subscribe account	<p>Click the button to subscribe the account you have been granted access to. Your permissions are shown in the text field.</p> <p><i>NOTE: In the case you have been granted access only to a single folder (or some but not all account folders), you can still click this button. This is useful in the case, you expect the account owner will grant access to other folder(s) to you in future.</i></p> <p><i>But in this moment, it does not give you any rights to other account folders.</i></p>

Uninstallation

To uninstall IceWarp Outlook Sync, follow these steps:


1. If running, close MS Outlook and launch the IceWarp Outlook Sync installer. It will detect IceWarp Outlook Sync is installed and switch to the uninstallation mode.
2. On the **Installation and maintenance** screen, select the **Uninstall** option and click the **Next** button.

Figure 1 – Installation and Maintenance Screen



3. On the **Uninstall summary** screen, review an uninstallation message and click the **Finish** button to close the wizard.

Figure 2 – Uninstall Summary Screen



Advanced IceWarp Outlook Sync Background

About

IceWarp Outlook Sync is based on a classical POP3/SMTP account. The SMTP account is set to use an existing IceWarp Server, whilst the POP3 account is set to be inactive. Therefore IceWarp Outlook Sync does not deal with sending emails at all. So digital signatures, encoding, invitation sending, etc. are handled by MS Outlook itself.

POP3 server is set to 127.0.0.1, port of 5110. IceWarp Outlook Sync listens on this port and simulates zero activity here. MS Outlook connects to this port from time to time and asks for new emails. IceWarp Outlook Sync always answers that there are not any new emails.

When performing synchronizations, IceWarp Outlook Sync connects to IceWarp Server using its own protocol to download/upload/update individual items.

It is recommended to create a "connector/sync" profile during IceWarp Outlook Sync installation – all necessary values are set within this process. The account created within this profile is the POP3/SMTP type one.

Mass Installations

It is recommended administrators to use the **.msi** file to perform remote mass installations (together with Active Directory Group Policy, a batch file or a third party tool). This installer sets all needed parameters – it is not necessary to set them manually.

Command Prompt Installations

It is also possible to run installation using Command Prompt. Use the **outlook-sync.exe** command with the following parameters:

Parameter	Description
--silent	installer will not show any interface, implies the --noprofile argument
--debug	installs debug version of Redemption, settings persist for update
--uninstall	installer uninstalls IW Outlook Sync from the machine, recommended with the --silent argument
--nodebug	installs release version of Redemption, settings persist for update
--log	installer produces installation logs to a file
Use with care	
--noprofile	installer will not ask for profile details and will not create a new profile
--noprofman	installer will not install a profile manager, use only if you are experiencing troubles with permission granting

Example: **outlook-sync.exe --silent**




NOTE: Redemption is a third party library for access to MS Outlook items and their properties.

Synchronization Progress Window

After Outlook Sync launch, its folders are synchronized with your server. In the case higher numbers of new items are synchronized, you may face a progress message window.

Figure 1 – Part of Progress Message



Meaning of numbers is as follows:

Downloaded X/Y: **Y** is the number of messages in the synchronization queue, waiting to be downloaded from the server, **X** is the number of currently downloaded messages (IceWarp Server to IceWarp Outlook Sync).

Uploaded X/Y: **Y** is the number of messages in Outlook, waiting to be appended to the server, **X** is the number of currently appended messages (IceWarp Outlook Sync to IceWarp Server).

Internal X/Y: **Y** is the number of messages already downloaded from the server and waiting to be imported to Outlook, **X** is the number of currently imported messages (IceWarp Outlook Sync to Outlook).